

PDF Stamp Command Line V1.0.0 User manual

Copyright (C) 2003 verypdf.com Inc
<http://www.verypdf.com/>
<mailto:support@verypdf.com>

PDF Stamp Command Line	1
V1.0.0 User manual	1
Introduction.....	3
Features	3
Limitations in the trial version.....	4
Running PDF Stamp with command-line options	4
1.Output and input file path	4
2.Text stamping.....	4
3.Image stamping	8
4.Page range	8
5.Register	8
Contact	9

Introduction

PDF Stamp is an advanced product that enables you to stamp content into a PDF document. Besides images, texts, PDF Stamp is able to add links. These processes can be realized in a determined number of pages with precise control over the size and position, the stamped text and/or images become a permanent part of each PDF document. There is no limit to the amount of stamps you could apply to a single document and no limit to the amount of documents you can stamp, as special feature you can integrate PDF Stamp into yourself programs (Include client side and Server side applications).

PDF Stamp lets you stamp watermarks such as "Confidential" on pages that include sensitive information or "Draft" on a preliminary PDF document to be distributed for review. You can stamp PDF document names, revision numbers, Date/Time stamps, bates numbering, pages numbers, contact information or any text that you need added to the file.

With the JPEG image support you can stamp company logos, author signatures, products, charts or any artwork in JPEG format. A Scale feature is provided with image stamping to easily increase or decrease the size of the stamped image, leaving the original image size intact.

Features

- Easy to use
- Windows 98, ME, NT, 2000 and XP support
- **Supports image stamp** (JPEG/TIFF/PNG images)
- **Supports text stamp**
- Output file (-o) — Duplicates the original file with the file name you specify. Stamps are placed in the duplicate file, leaving the original copy unchanged
- Stamp pages using the standard Base 14 fonts and system font.
- Supports Font Style, Font Size, Text Modes (solid, outline), Grayscale and **RGB** Color (0-255 **RGB** color values supported)
- Top, bottom, vertical center, diagonal-top left and diagonal-bottom left .
- Stamps can be placed in the exact vertical center of a page (or the exact vertical center within a individual stamping space)
- Enabling you to easily position the stamp in any location on the page
- Stamp on Top of or Underneath the original PDF document page contents
- Text and Image can be stamped on **any angle**. Any positive or negative numbers, including decimal numbers may be used to specify an angle in degrees
- Specify Start and Ending page numbers
- As an alternative to specifying static values for the text, you can use stamping variables to stamp dynamic data. Dates, times, page numbers; file names are just a few of the variables available. See the PDF Stamp documentation for a listing of all Stamping Variables.
- Supports multiple line text stamps within one stamp item

- JPEG/TIFF/PNG image size can be increased or decreased. No need to adjust the image size in another application before the stamp
- Wrap text to a new line if it would otherwise be too long to fit in its margined area
- **Supports web links**
- **Justification (when multi text)**— Left, right, or center

Limitations in the trial version

- Insert a watermark string in the every page in the PDF file

Running PDF Stamp with command-line options

pdfstamp.exe

```
[<-PDF> <file> [-O <file>]]  
[<-AT> <string> [-Pn] [-MLRn] [-MTBn] [-Rn] [-L] [-U <url>]  
                  [-Cn] [-H] [-FNn/-FT <name>] [-FSn] [-ML/-MR/-MC]]  
[<-AI> <string> [-Pn] [-MLRn] [-MTBn] [-Rn] [-L] [-U <url>]  
                  [-Wn] [-Hn]]  
[<-AI>...] [<-AT>...] [...]  
[<-SR> [-Sn] [-En]]  
[<-REG> <string>]
```

1. Output and input file path

-PDF <input file>

Open an existing PDF file to stamp.

-O <output file>

Write output to a new file, the default is stamp on the input PDF file.

2. Text stamping

-AT

Creating a Text Stamp.

<string>

String is the content of the stamp that you will create. In your stamp the text to be stamped must be enclosed in quotation mark, as with all other parameters in the stamp content. Type text exactly as you want it to appear. With the following for Text in your stamp content:

-AT "Copyright verypdf.com Inc"

Using variables in stamp content

When you are working with documents, there is a lot of information that varies from document to document — dates, times, filenames, etc. Even within a document there are things that change from page to page, such as page numbers or headers and footers. PDF Stamp software provides a large series of variables that access this dynamic information and stamp it into your document.

Note: All variables must be preceded by the slash (\) character. If the \ character is missing, the variable name will appear in the stamped text. If you want to use the \ character in a stamp it must be listed in the stamp file as \\.

Below is a table of all variables available showing the variable name, what it does, and an example.

Variable	Format	Example Output
\t	Local time	e.g. 10:10:10
\d	Local date	e.g. 2003-7-6
\p	Current page number	Maybe “Page \p” equal “Page 3”
\c	Total page number	Maybe “Total \c” equal “Total 3”
\T	Title of this PDF	
\A	Author of this PDF	
\S	Subject of this PDF	
\n	New line. Use for multi-line stamps	Sample stamp, line1 Sample stamp, line2 Sample stamp, line3
\\	\ (Use when stamp must include percentage symbol)	\

-Pn (default is -P1)

-Pn identifies where on the page the stamp item will appear. Allowed values are Top, Bottom, Top-Left, Bottom-Left, Center etc. If Position is not included in the stamp option, PDF Stamp will use the default, Top-Left, and the stamp will appear at the Top-Left of the page.

-Pn	Meaning
-P1	Stamps on the Top-Left of the page. (default)
-P2	Stamps on the Top-Center of the page.
-P3	Stamps on the Top-Right of the page.
-P4	Stamps on the Right-Center of the page.
-P5	Stamps on the Right-Bottom of the page.
-P6	Stamps on the Bottom-Center of the page.
-P7	Stamps on the Left-Bottom of the page.
-P8	Stamps on the Left-Center of the page.
-P9	Stamps on the Center of the page.

[-MLRn] [-MTBn]

Offset from current position, n is an offset value, **default n equal zero**,

-MLRn: Move to left or right n point
 -MTBn: Move to top or bottom n point

For example:

.e.g -MLR10 Move to right 10 point
 .e.g -MLR-10 Move to left 10 point
 .e.g -MTB10 Move to bottom 10 point
 .e.g -MTB-10 Move to top 10 point

-Rn (default is -R0)

The Angle parameter provides more flexibility for stamp positioning. While a diagonal stamp will angle text at 45 degrees, the Angle parameter may be used to position a text or image stamp at any angle.

.e.g -R45 or .e.g -R-45



-R45

-Cn (default is -C0)

Specify the text color, range from 0x000000-0xFFFFFFFF, in hex.

.e.g -C255

-L (default is top most of all layers, overlay)

Use the -L parameter to stamp under the existing text and/or graphics of the input PDF document; the default is top most of all layers.




underlay



Overlay

-H

Set Text mode option, if set this option, the text mode is **Outline**, default is **Solid** mode.



-FNn/-FT name

Set Text font name, default is **Times-Roman**, you only can use one of them in one time,

-FNn can be specified one of the following values,

Font code (-FNn)	Font Name
-FN100	Times-Roman
-FN101	Times-Bold
-FN102	Times-Italic
-FN103	Times-Bold-Italic
-FN200	Courier
-FN201	Courier-Bold
-FN202	Courier-Oblique
-FN203	Courier-Bold-Oblique
-FN300	Helvetica
-FN301	Helvetica-Bold
-FN302	Helvetica-Oblique
-FN303	Helvetica-Bold-Oblique
-FN400	Symbol

“-FT name” select a system font which installed in your system, for example, **-FT "Arial"**.

-FSn (default is -FS16)

Set the font size, default is 16 point, for example,
e.g. -FS16

-ML/-MR/-MC (default is -MC)

-ML/-MR/-MC are used to align text on document pages, it only available for multi-line text stamps,

- ML:** left alignment
- MR:** right alignment
- MC:** center alignment

-U <url>

Add a web link to a target URL on the Web.

For example: **-U "http://www.verypdf.com"**.

Note: **-U** parameter doesn't support font and image rotation.

3. Image stamping

-AI

Image stamping

<string>

String is the parameter that tells PDF Stamp software where to find the JPEG/PNG/TIFF image file to stamp; it must be a full path, for example,

-AI "C:\input.jpg"

-Wn (default is -W100)

-Wn parameter is used to increase or decrease the **width** of the original image when it is stamped onto the PDF document. A scale of 50 will make the image half (50%) its original **width**, while scales of 200 (200%) will double it.

-Hn (default is -H100)

-Hn parameter is used to increase or decrease the **Height** of the original image when it is stamped onto the PDF document. A scale of 50 will make the image half (50%) its original **Height**, while scales of 200 (200%) will double it.

[-Pn] [-MLLn/-MRRn/-MTTn/-MBBn/-MRBn/-MLTn/-MRTn/-MLBn] [-Rn] [-L] [-U <url>]

Please refer to **-AT** options; these parameters are the same with the **-AT**.

4. Page range

-SR

Pages to Stamp — Specify Start page and page count, default is from first page to maximum page number.

-Sn (default is -S1)

Start page number.

-En (default is maximum page)

page count.

e.g. **-SR -S3 -E5**

5. Register

-REG <string>

Register pdfstamp soft.

Length of string must be 16 bytes.

e.g. **-REG "ABCDEFGHJKLMNOP"**

Contact

Homepage

<http://www.verypdf.com/pdfstamp/>

<http://www.toppdf.com/pdfstamp/>

E-mail

<mailto:support@verypdf.com>